


Navigation Menu Widget

Widget Use

Renders the product category menu, in which all subcategories expand from one top level category menu item.

 **Please note**
To view widget updates on your website, refresh the Template cache. see: [Cache refreshing](#)

Example of Widget Use

Desktop drop-down mode

Product Categories

Our Store

Sports & Outdoors

Office Products

Office Furniture

Fitness

Writing

Chairs

Tennis Equipment

Paper

Desks

Cricket Equipment

Stationery

Mobile Pedestals

Camping

Labelling & Filing

Meeting & Conference Tables

Work Clothing

Hard Drives & Data Storage

Storage Cabinets

Shirts & Polos

Early Childhood

Outerwear

Puzzles

Footwear

Music

Pants

Literacy


Shorts

Games

Gross Motor Skills

Numeracy

Desktop - flyout mode



Where can the Widget be placed?

The widget can be used in the following templates:

- [Theme Layout Template](#)

Widget Options

Option	Use	Comments	Available from Version
Description	A short specific description of this widget's use.	This description is added to the widget title. It makes the widget's use clear on the template page.	All
Layer	The layer the widget is valid for.	Use layering to limit widget content to certain groups of users. To use the same widget for more than one user group but with different options set, add the widget as many times as needed in the same zone. Then add layering to define the user group each time.	All
Append / Prepend Category Menu?	Determines whether the category menu is inserted at the beginning or end of the site's main menu. <ul style="list-style-type: none"> • Prepend - inserts the Category menu in first position • Append - inserts the Category menu in last position 	Default: Prepend	All
Insert Category At Location	This will override the Append / Prepend setting and insert the category menu at this particular location on the menu.	Locations are expressed numerically, so the first menu position would be 00, next 01, third would be 02, and so on.	All
Category Menu Levels	The number of category levels to be displayed in the menu.	Default: 2	All
Max Number Of Columns	The maximum number of category columns to be displayed under the top level menu item.	Default: 4	All
Product Category Menu Text	The text for the top level category link.	Default: Product Categories	All

Product Category Menu Link	The URL for the page the top category menu item links to.	Default: blank	All
Product Category Menu Icon	The icon displayed to the left of the Product Category Menu text.	Default: blank	All
Product Category Menu List	A comma-separated list of categories to be displayed in mega menu format, instead of the Product Category Menu text with all categories beneath.	Default: Example: SX04,SX01,SX02	All
Add SEO URL for product category menu?	Determines whether an SEO URL is added for the product category menu.	Default: disabled Toggle to enable	
Category URL Prefix	The prefix inserted into the category URL before the category name. Primarily used during existing site upgrades to BPD, where it is desirable to maintain existing URLs.	Default: blank Example: /category	All
Show Single Column for 2 Level Categories?	Determines whether just the upper level category is displayed in cases where the category consists of 2 levels.	Default: disabled Toggle to enable	All
Use Manual Column Sequencing?	Determines whether to use manual assignment of categories into columns. When enabled in Integrated mode, sort sequence is derived from Category Maintenance program in PRONTO. In Online mode, the user can manually assign categories to columns in the CMS.	Default: disabled Toggle to enable	Online mode 4.31
Show Category List Title?	When there are custom templates displayed within the category drop-down, enable this to display a title above the category list.	Default: disabled Toggle to enable	All
Render Mode	Determines the style in which the menu is rendered: drop-down or flyout. (See examples above.)	Default: drop down	4.01
Render Custom Sections?	When there are custom templates available for display around a menu section, enable this option to render them.	Default: disabled Toggle to enable	
Render Mobile Menu?	Determines whether the navigation menu should be displayed on mobile devices.	NOTE - If the flyout-style Mobile Menu widget has been added to the Theme Layout, we recommend this setting be unticked so the navigation menu does not render on mobiles. Default: enabled Toggle to disable	All
Titles			
Category List Title	The text for the Category List Title.	Default: Product Categories	All
Category List Title Link	The URL for the Category List Title link.		All
Mobile-only Content			
Login Prompt	The text for the login link on mobile.	Default: Login	All
Logout Prompt	The text for the logout link on mobile.	Default: Logout	All
Register Prompt	The text for the registration link on mobile.	Default: Register	All
My Account Prompt	The text for the dashboard page link.	Default: My Account	All
My Account Page	When populated, inserts a mobile menu item linking to a dashboard page for logged in users.	Example: /dashboard	All
Login Page	The page the login link redirects to on mobile for public users.	Default: /login	All
Register Page	The page the register link redirects to on mobile for public users.	Default: /register	All

Related help

- [What is the Theme Layout?](#)

Menus

- [Add a page to the CMS](#)
- [Section Menu Editor](#)
- [Add items to the Mega Menu](#)
- [Mega Menu Content Tiles](#)
- [Linking a Menu to a Role](#)
- [Add a New Menu Item](#)

Related widgets

- [Section Menu Widget](#)
- [Navigation Menu Widget](#)
- [Mega Menu Widget](#)
- [Mobile Menu Widget](#)
- [Mobile Menu Zoned Widget](#)
- [Category Menu Widget](#)
- [BPD Mobile Menu](#)
- [Product Category List Static Widget](#)
- [Page Title Dynamic Widget](#)
- [Dashboard Widget](#)
- [Role Select Widget](#)
- [Outstanding Tasks Display Widget](#)