Braintree Credit Card Settings




Braintree Payments

See: documentation on Braintree Payments for other help topics.

Commerce Vision's Braintree Payments gateway is integrated to accept Visa, Mastercard and American Express. Specific settings for each credit card type are not required as they are managed within Braintree

Credit cards processed by the Braintree gateway are found under the Payment Methods tab in the Payment panel. It is possible to have a non-Braintree credit card gateway active at the same time unless payment processing is set to Braintree only.

Vaulting options are also available for credit cards.



Configure Credit Card Settings

To configure Braintree Credit Card Settings:

- 2. If the Available in CMS toggle is not enabled, toggle it ON.
- 3. Click Configure.

On this page:

- Configure Credit Card Settings
- Test Credit Card Gateway
- Additional Information
- Related help

4. Scroll down to Credit Card Settings.

Credit Card Settings
Specify the credit card Settings

	Enable Credit Card	Overrides	0
Ø 🖊			
	Allow Vault Credit Card	Overrides	0
Ø /			
	Allow Vault Credit Card Override	Overrides	0
Ø /			
	Require Credit Card Holder Name	Overrides	0
9.4			

Enable Credit Card - toggle ON to offer payment by credit card through the Braintree gateway. When enabled, the
Payments panel in the checkout page displays 'Pay with card' as an option. Logos of currently accepted credit cards
are automatically listed.



- Allow Vault Credit Card and Allow Vault Credit Card Override work together to determine the default vaulting setting and whether Users are permitted to override it.
 - Allow Vault Credit Card sets the default vaulting option when a credit card is used successfully. Toggle ON to vault a card by default.
 - b. Allow Vault Credit Card Override allows the User to override the default option set in Allow Vault Credit Card. If toggled ON, a Save card checkbox is displayed for the User to override the default. Whether the checkbox is preselected or not depends on what has been set as the default.



This table summarises the four possible vaulting configurations:

	Allow Vault Credit Card		
Allow Vault Credit Card Override	ON	OFF	
ON	Default vaulting: yes	Default vaulting: no	
	Checkbox: displayed, not ticked	Checkbox: displayed, ticked	
	 A card will be vaulted by default unless the User unticks the checkbox. 	A card will not be vaulted by default unless the User ticks the checkbox.	
OFF	Default vaulting: yes	Default vaulting: no	
	Checkbox: not displayed	Checkbox: not displayed	
	A card will be vaulted by default. The User cannot override this.	A card will be not be vaulted. The User cannot override this.	

7. Require Credit Card Holder Name - Toggle ON if the cardholder's name must be entered during the payment process. TIP - If this setting is OFF, the Cardholder Name is left blank in the transaction record in your Braintree account .



8. To save your settings, click Save.

Test Credit Card Gateway

You can test the sandbox environment using specific credit card numbers. See: Braintree Test Credit Card Numbers

Additional Information

Minimum Version Requirements	4.31	
Prerequisites	Braintree Account, third party payment accounts	
Self Configurable	Yes	
Business Function	Payment Types	
BPD Only?	Yes	
B2B/B2C/Both	Both	
Third Party Costs	Fees may apply	

Related help

- Braintree Payments
- Braintree Vaulting
- Braintree Payment Settings

- Braintree Payment Settings
 Braintree PayPal Settings
 Braintree Google Pay Settings
 Braintree Apple Pay Settings
 Braintree Payments Credit Card Data Flow
 Braintree Test Credit Card Numbers