# **Navigation Button Widget**

#### Widget Use

Adds a styled button that can link to any page on your site or externally. You can add an icon to the button and configure elements such as colour, size and icon position.

### Example of Widget Use

• Keep Shopping!

#### Where can the Widget be placed?

All templates

## Widget Options

Option	Use	Comments	Available from Version
Description	A short description of the widget's use.	This description is added to the widget title. It makes the widget's use clear on the template page.	All
Layer	The layer the widget is valid for.	Use layering to limit widget content to certain groups of users. To use the same widget for more than one user group but with different options set, add the widget as many times as needed in the same zone. Then add layering to define the user group each time.	All
Button Label	Text on the button.		All
Button Icon	Icon on the button.	Default: cv-ico-general-arrow-left6 Select via drop-down	All
Icon Position	Icon position relative to the text on the button.	Default: Left	All
Button Colour Type	Styles the button colour in line with site design. Options: • Alternate • Black • Default • Primary • Secondary	Default: Primary TIP - If you are not sure what your colour selection is, refer to your Style Guides. (In the CMS, go to <b>Content Style Guides UI Elements</b> . Scroll down to Buttons - Standard.)	All
Button Colour Shade	Styles the button shade in line with site design. Options: • Dark • Light • Normal	Default: Normal	All

Button Type	Styles the button type in line with site design. Options: Clear Ghost Normal Square Pill	Default: Normal	All
Button Size	Styles the button size in line with the site design. Possible values: • Normal • Small • Large	Default: Large	All
Link Location	Where the button links to: • Home Page • Previous Page • Cart • Custom Page	Default: Previous Page	All
Custom Page Url	Enables the button to link to any page. <b>NOTE -</b> If a custom page URL is entered, this will override any non-custom page Link Location selected.	Default: blank	3.84
Link Target	Select from: • Blank • Current Frame • Top Frame • Parent Frame	<ul> <li>Default: Current Frame</li> <li>TIP - Blank or Current Frame is typically used. Top Frame and Parent Frame are for advanced users.</li> <li>Blank: new window/tab</li> <li>Current Frame: page opens in the same window as link.</li> <li>Top Frame: page opens in the full body of the window.</li> <li>Parent frame: page opens in the immediate parent of the frame. It is used when there may be several nested frames and this allows more control over which frames are specified.</li> </ul>	4.37